

## BMS BACnet Documentation =====

Version: 1.0 Date: 2025-12-24

Overview ----- This document provides: - Developer reference for the BACnet-specific modules: - ``bms_bacnet_server_bacnet.py`` (BACnet server) - ``bms_bacnet_client_bacnet.py`` (BACnet client) - ``bms_bacnet_demo_bacnet.py`` (end-to-end demo) - Usage and tutorial for running the simulator on the same machine and across networked machines - Database storage behavior used by the client - Troubleshooting and best practices

Recommended Python runtime ----- - Recommended: Python 3.11 (bacpyes compatibility tested up to 3.11). Python 3.12 may not be supported by some bacpyes releases due to removal of ``asyncore`` and other changes.

Files described ----- 1) ``bms_bacnet_server_bacnet.py`` — BACnet server

Purpose - Expose the simulated BMS device sensor values as BACnet objects via ``bacpyes``. - Maps each sensor to an ``AnalogValueObject`` (temperature, humidity, pressure, CO2, occupancy). - Updates each object's ``presentValue`` from the running BMS simulator (``BMSDevice.get_sensor_data()``).

Key classes/usage - ``BACnetBMSServer(device, address='127.0.0.1/47808', device_id=12345)`` - ``start(poll_interval=1.0)`` — starts bacpyes core in background and an update thread that polls the simulator at ``poll_interval`` seconds. - ``stop()`` — stops the update thread and attempts to stop bacpyes core.

Important details - Requires ``bacpyes`` installed and a compatible Python version (3.11 recommended). - The server registers 5 analogValue objects with instance numbers 1-5 mapping to sensors: - 1: temperature - 2: humidity - 3: pressure - 4: co2\_level - 5: occupancy - The analog object ``presentValue`` is updated every ``poll_interval`` seconds by reading ``device.get_sensor_data()``.

2) ``bms_bacnet_client_bacnet.py`` — BACnet client

Purpose - Minimal ``bacpyes`` client wrapper to perform ``ReadProperty`` requests (reads ``presentValue``) from remote analogValue objects. - Automatically stores each read into an SQL database (SQLite by default) via ``DBHandler``.

Key classes/usage - ``BACnetBMSCient(local_device_id=999, local_address='0.0.0.0/47809', db_config=None)`` - ``start()`` — starts bacpyes core in a background thread. - ``stop()`` — stops bacpyes core. - ``read_analog(target_address, object_type, instance, timeout=2.0)`` — synchronous read of the ``presentValue`` property on the remote object. Returns bacpyes response (and also writes a row to the configured DB).

Database integration (DBHandler) - Default database: SQLite file ``bms_bacnet.db`` in the working directory. - Default table: ``bms_readings`` - Columns: ``id``, ``timestamp``, ``device``, ``object_type``, ``instance``, ``sensor_name``, ``value`` - ``DBHandler`` supports two ``db_type`` values: ``sqlite`` (default) and ``postgres`` (requires ``psycopg2`` and valid DB credentials). - When ``read_analog`` returns a value, the client attempts to convert it to ``float`` and insert it as the ``value``; if conversion fails the string representation is stored.

Examples - Default (SQLite) client usage:

```
from bms_bacnet_client_bacnet import BACnetBMSCient
```

```
client = BACnetBMSCient() client.start() val = client.read_analog('127.0.0.1/47808', 'analogValue', 1)
print('Read result:', val) client.stop()
```

- Explicit DB config example (Postgres):

```
db_cfg = { 'db_type': 'postgres', 'database': 'bacnetdb', 'user': 'bacnet_user', 'password': 'secret', 'host':
'192.168.1.10', 'port': 5432, 'table': 'bms_readings' } client = BACnetBMSCient(db_config=db_cfg)
```

3) `bms\_bacnet\_demo\_bacnet.py` — end-to-end demo

Purpose - Convenience script that starts a `BMSDevice` simulator, the `BACnetBMSServer`, and a `BACnetBMSClient` that reads the temperature (analogValue, instance 1) 5 times. - Intended for local single-host validation.

Usage - Run the script directly (after installing dependencies and creating a simulator file):

```
C:/Python311/python.exe bms_bacnet_demo_bacnet.py
```

Tutorials ----- A. Run everything on the same machine (recommended for first test)

1. Create a venv and install requirements for BACnet:

```
cd c:\Users\hamid\pyCode C:/Python311/python.exe -m venv .venv-bacnet
.\venv-bacnet\Scripts\Activate.ps1 pip install -U pip pip install -r requirements_bacnet.txt
```

**also ensure your bms\_simulator.py,  
bms\_bacnet\_server\_bacnet.py,  
bms\_bacnet\_client\_bacnet.py,  
bms\_bacnet\_demo\_bacnet.py are in the folder**

2. Run the demo (single command):

```
C:/Python311/python.exe bms_bacnet_demo_bacnet.py
```

3. Observe output like:

```
Read temperature (analogValue,1): 22.14 Read temperature (analogValue,1): 22.01 ...
```

4. Inspect database (SQLite default) in working folder: `bms\_bacnet.db`. - You can view using sqlite3 CLI or a GUI tool.

B. Run server and client on separate machines (networked)

Assume host A (server) has IP `192.168.1.10`, host B (client) has IP `192.168.1.11`.

1. On host A (server): - Ensure Python 3.11 and `baccypes` installed. - Start server with address binding to host A's interface and correct transport port. Example: `192.168.1.10/47808`.

## on host A

```
from bms_simulator import BMSDevice from bms_bacnet_server_bacnet import BACnetBMSServer
dev = BMSDevice('BACNET-DEV1', 'Floor 1') dev.start_simulation() server = BACnetBMSServer(dev,
address='192.168.1.10/47808', device_id=4001) server.start()
```

## keep running

2. On host B (client): - Ensure Python 3.11 and `baccypes` installed. - Use the client's `read\_analog` pointing to `192.168.1.10/47808`.

```
from bms_bacnet_client_bacnet import BACnetBMSClient
client = BACnetBMSClient(local_device_id=999, local_address='0.0.0.0/47809') client.start() val =
client.read_analog('192.168.1.10/47808', 'analogValue', 1) print('Remote temperature:', val)
client.stop()
```

Networking notes - Ensure firewall rules on host A allow the chosen UDP/TCP transport and port (bacypes example uses BIP/UDP-style addresses like `ip/port`). - Use stable IPs or hostnames. - For NAT or cross-network communications, configure routing and firewall accordingly.

Database notes - The client writes readings on each successful `read\_analog` call. - For SQLite: concurrent writes from multiple processes may be serialized or cause locks — for multi-client writes to a shared DB prefer PostgreSQL.

Troubleshooting ----- - "ModuleNotFoundError: bacypes": verify virtualenv is active and `pip install bacypes` completed. - "Connection refused" or "No response": ensure server is running and address/port match; verify firewall rules. - "Port already in use": pick a different port and update server/client addresses accordingly. - Database insertion errors: check DB credentials and that `psycpg2` is installed for Postgres.

Converting this doc to PDF ----- A small helper script `generate\_bacnet\_pdf.py` is provided to convert this Markdown into a simple PDF (requires `reportlab`). See the script and instructions in the project root.

License & credits ----- This documentation accompanies the BMS simulator project and is provided as part of the workspace.

End of document